









Garden Dreamer Garden

FABRICS DESIGNED BY





GRD-79901 TERRA FIRMA



GRD-79903 FLOWER WALTZ



GRD-79905 DIAMOND FRAGMENTS



GRD-79908 TRIANGULAR-IMPRESSION



GRD-89901 TERRA-FIRMA-HUMID



GRD-89903 FLOWER DANCE



GRD-89907 CLIMBING POSIES BLUSH

ADDITIONAL BLENDERS FOR THIS PROJECT



DEN-S-2002 COOL FOLIAGE



DEN-S-2003 AFTERNOON SAIL





FABRIC REQUIREMENTS

Fabric A	GRD-89903	½ yd.
Fabric B	BSC-79908	½ yd.
Fabric C	GRD-89901	½ yd.
Fabric D	GRD-79903	½ yd.
Fabric E	GRD-89907	⅓ yd.
Fabric F	BSC-79901	⅓ yd.
Fabric G	DEN-S-2003	¾ yd.
Fabric H	DEN-S-2002	¾ yd.
Fabric I	GRD-79905	½ yd.

BACKING FABRIC
GRD-79905 1 1/4 yds (Suggested)

BINDING FABRIC
Fabric | GRD-79904 (Included)

CUTTING DIRECTIONS

1/4" seam allowances are included. WOF means width of fabric.

- Eight (8) 67/8" squares from fabric A.
- Two (2) 67/8" squares from fabric B.
- Two (2) 6% squares from fabric **C**.
- Eight (8) 4" squares from fabric D.
- Eight (8) 21/2" squares from Fabric E.
- Eight (8) 2½" squares from Fabric F.
- Eight (8) 4" squares from fabric G.
- Four (4) 6%" squares from fabric G.

 Three (3) 2½" x WOF strips from Fabric H, Sub-cut one (1) strip in halves.

• Two (2) 2½" x 16½" strips from Fabric **H**.

CONSTRUCTION

Sew all rights sides together with ¼"seam allowance.

- Start with the construction of the HST's needed for the table runner top.
- Take one (1) 6% square from fabrics A and G.
- Place the squares together right side of fabrics together and align them.







DIAGRAM 1

- Use a fabric marker to trace a diagonal line across the square on top.
- $^{\circ}$ Sew $^{1}\!\!/\!_{4}$ " away from both sides of the drawn line.
- Use the rotary cutter and clear ruler to cut on top of the drawn line.







 ${\rm DIAGRAM}~2$

 Press open, make a total of eight (8) AG HST's.



x8

DIAGRAM 3

- Repeat the previous steps to construct four (4) **AB** and **AC** HST's.
- · Set aside.





DIAGRAM 4

- Take one (1) AG HST's and one (1) 4" square from fabric D.
- Place fabric D square right sides of fabrics togehter on top of the AG right bottom corner.
- Sew accross **D** square from bottom left corner to right upper corner.
- Trim excess fabric.
- · Fold and press.











DIAGRAM 5

- Take one (1) 2½" square from fabric E.
- Place fabric E square right side of fabrics together on top of the AGD square right bottom corner.
- Sew accross **E** square from bottom left corner to right upper corner.
- Trim excess fabric.
- · Fold and press.
- Make a total of eight (8) set aside.









 ${\rm DIAGRAM}~6$

- Repeat the previous steps using the remaining AB and AC HST's as shown in the diagram below.
- Make a total of four (4) from each combination.





DIAGRAM 7

 Attach the squares together, mirroring each other to create a triangular shape as shown in the diagram below.



x4



x2



DIAGRAM 8

 Attach the units together as shown in the next diagram.



DIAGRAM 9

- Take two (2) 2½" x WOF strips and the two (2) halves from fabric H.
- Attach each half to each of the 2½" x WOF strips, trim it to end up with two (2) 48" strips.
- Attach the strips to each side of the top unit.



DIAGRAM 10

- Take two (2) 2½" x 16½" strips from fabric **H**.
- Attach each strips to the top and bottom edge of the top unit.





DIAGRAM 11

RUNNER ASSEMBLY

Sew rights sides together.

 Place BACKING FABRIC on a large surface wrong side up. Stretch it with masking tape against that surface.


- Place BATTING on top of backing fabric.
- Place TOP on top of the batting with right side facing up. Smooth away wrinkles using your hands.
- Pin all layers together and baste with basting thread, using long stitches. You can also use safety pins to join the layers.
- Machine or hand quilt starting at the center and working towards the corners. Remember that quilting motifs are a matter of personal preference. Have fun choosing yours!
- After you finished, trim excess of any fabric or batting, squaring the quilt to proceed to bind it.

BINDING

Sew rights sides together.

- Cut enough strips 1½" wide by the width of the fabric I to make a final strip 146" long. Start sewing the binding strip in the middle of one of the sides of the quilt, placing the strip right side down and leaving an approximated 5" tail. Sew with ¼" seam allowance (using straight stitch), aligning the strip's raw edge with the quilt top's raw edge.
- * Stop stitching ¼" before the edge of the quilt (DIAGRAM B 1). Clip the threads. Remove the quilt from under the machine presser foot. Fold the strip in a motion of 45° and upward, pressing with your fingers (DIAGRAM B2). Hold this fold with your finger, bring the strip down in line with the next edge, making a horizontal fold that aligns with the top edge of the quilt (DIAGRAM B3). Start sewing at ¼" of the border, stitching all the layers. Do the same in the four corners of the quilt.

- Stop stitching before you reach the last 5 or 6 inches. Cut the threads and remove the quilt from under the machine presser foot. Lay the loose ends of the binding flat along the quilt edge, folding the ends back on themselves where they meet. Press them together to form a crease. Using this crease as the stitching line, sew the two open ends of the binding with right sides together (you can help yourself marking with a pencil if the crease is difficult to see).
- Trim seam to ¼" and press open. Complete the sewing. Turn binding to back of the quilt, turn raw edge inside and stitch by hand using blind stitch.



Congratulations & enjoy



artgalleryfabrics.com

NOTE: While all possible care has been taken to ensure the accuracy of this pattern, We are not responsible for printing errors or the way in which individual work varies.

Please read instructions carefully before starting the construction of this quilt. If desired, wash and iron your fabrics before starting to cut.

© 2021 Courtesy of Art Gallery Quilts LLC. All Rights Reserved.