

POT HOLDER & KITCHEN TOWEL SET





LOVE 2 LOVE POT HOLDER & KITCHEN TOWEL SET DESIGNED BY AGEstudio







FUS-RW-1900 SWIFTING FLORA ROSEWOOD



MTM-9100 INDICATION BERRY



LVS-48807 HEARTS FLETCHING GOLD



LTO-8234 SEASON CAROLS



FUS-RW-1901 BOKEH LATTICE ROSEWOOD



SNT-33102 JOSEPHINE POETIC



OPH-14356 WRITTEN LOVE LOUD



FAV-85846 CENTRAL PARK SWEET



PPE-340 HAPPILY EVER AFTER



DSE-721 CORAL ROSE



FUS-A-406 HE LOVES ME ABLOOM



DSE-720 PEACH WHISPER





FINISHED SIZE | 7½" × 7½", 15" × 15"

FABRIC REQUIREMENTS

Fabric A	FUS-SW-1900	FQ.
Fabric B	MTM-9100	FQ.
Fabric C	LVS-48807	FQ.
Fabric D	LTO-8234	FQ.
Fabric E	FUS-RQ-1901	FQ.
Fabric F	SNT-33102	FQ.
Fabric G	OPH-14356	FQ.
Fabric H	FAV-85846	FQ.
Fabric I	PPE-340	FQ.
Fabric J	DSE-721	FQ.
Fabric K	FUS-A-406	FQ.
Fabric L	DSE-720	FQ.

ADDITIONAL MATERIAL

Insulated Batting Foam Board

CUTTING DIRECTIONS

1/4" seam allowances are included. WOF means width of fabric.

Pot Holder

- Five (5) 12" x 2" strips from fabric A.
- One (1) 18" x 8" rectangle from fabric B (binding).
- Two (2) 10" x 1½" strips from fabric **B** (pocket binding).

- One (1) 9" square from fabric C.
- Five (5) 12" x 2" strips from fabric C.
- One (1) 3½" x 1½" strip from fabric C (loop).
- Two (2) 18" x 5" rectangles from fabric D.
- Five (5) 12" x 2" strips from fabric D.
- Four (4) 12" x 2" strips from fabric E.
- Four (4) 12" x 2" strips from fabric G.
- One (1) 18" x 8" rectangle from fabric **H** (binding).
- Two (2) 10" x 1½" strips from fabric **H** (pocket binding).
- Four (4) 12" x 2" strips from fabric J.
- Two (2) 18" x 5" rectangles from fabric K.
- Five (5) 12" x 2" strips from fabric K.
- One (1) 9" square from fabric L.
- Four (4) 12" x 2" strips from fabric L.
- One (1) 3½" x 1½" strip from fabric **L** (loop).

Napkins:

- One (1) 15½" square from fabric F.
- Four (4) heart template from fabric F.
- One (1) 15½" square from fabric I.
- Four (4) heart template from fabric I.
- Two (2) $15\frac{1}{2}$ " x $3\frac{1}{2}$ " rectangles from fabric J.

CONSTRUCTION

Pot Holders Construction

- Start by taking all of your 12" x 2" strips from fabrics A, C, D, E, G, J, K and L and fold the edges ½" towards the center making sure the wrong side of the fabric is hidden.
- Press




DIAGRAM 1

Pot Holder 1

- Take a 9" x 9" foam-board and draw two intersecting guide lines meeting in the center.
- Take a piece of fusible interfacing bigger than the foam board and place it on top of the foam-board with the fusible side looking up.
- Take one (1) strip from fabric A, place it on top of the fusible interfacing aligned to the horizontal line. Use pins on both ends to secure the strips in place.
- Take another strip from fabric A, and place it next to the previous strip making sure you leave no space in between the fabric strips and pin it.




DIAGRAM 2

 Take the remaining strips from fabric A and L and place them in the order shown on the diagram below.





DIAGRAM 3

- Now, start weaving fabrics D and E between the strips of fabrics A and L on the perpedicular vertex.
- Follow the diagram below for each fabric placement.
- Pin the strips to hold them in place.



- Once finished, tape the edges with masking tape and remove the pins.
- Press the fusible interfacing to the fabrics gluing it all together.
- Take template 1 and place it on top of the weaved piece and using a fabric pen trace your template circle.
- Remove the piece from the foam board and sew at ½" in from the marked line, that way you secure better the piece and then cut at the marked line.




DIAGRAM 5

Pot Holder 2

- Take the same 9" square foam-board that you previously used.
- Take a piece of fusible interfacing bigger than the foam board and place it on top of the foam-board with the fusible side looking up.
- Take one (1) strip from fabric C, place it on top of the fusible interfacing aligned to the horizontal line.
- Take another strip from fabric C, and place it next to the previous strip making sure you leave no space in between the fabric strips and pin it.




DIAGRAM 6

 Take the remaining strips from fabric C and G and place them following the diagram below.





DIAGRAM 7

- Now, start weaving fabrics J and K between the strips of fabrics C and G on the perpedicular vertex.
- Follow the diagram below for each fabric placement.
- Pin the strips to hold them in place.



- Once finished, tape the edges with masking tape and remove the pins.
- Press the interfacing to the fabrics gluing it all together.
- Take template 1 and place it on top of the weaved piece and using a fabric pen trace your template circle.
- Remove the piece from the foam board and sew at ½" in from the marked line that way you secure better the piece and then cut at the marked line.




DIAGRAM 9

Creating the loop:

- Take one (1) 3½" x 1½" strip from fabric C and L.
- Fold the edges to the center for fabric C strip and then fold in half.
- Sew the edges with matching thread.
- Repeat the same process for fabric L strip.




DIAGRAM 10

- Take one (1) 9" square from fabric C and a piece of insulated batting and quilt as desired.
- Take template 1, trace and cut your piece.




DIAGRAM 11

- Fold the 3½" loop in half to create a loop and place it with the raw edge touching the raw edge of fabric and on its middle point.
- Stitch on the edge at a ½" seam allowance in order to hold your loop.





DIAGRAM 12

 Repeat the same process for pot holder 2 with fabric L.



- Place fabric C piece and pot holder 1 wrong sides facing together and baste stitch all around.
- Repeat the same for pot holder 2 and fabric
 piece .




DIAGRAM 14

- Take two (2) 18" x 5" rectangles from fabric K and one (1) piece of batting. Layer one (1) rectangle from fabric K, wrong side facing up, one (1) rectangle of batting and another rectangle from fabric K, wrong side facing down.
- Pin your pieces and quilt as desired.
- Then, take template 2 and trace it. Cut your pocket pieces, you will have two (2) pot holder pockets.




DIAGRAM 15

 Repeat the same process for fabric D pot holder pockets. These will be for pot holder 2.



DIAGRAM 16

Take two (2) 10" x 1½" strips of fabrics B and
 H and bind the straight edges of fabric D and fabric K pocket pieces.

• Trim excess fabric if needed.




DIAGRAM 17

- To bind your pot holders, you will need to cut your binding on the bias.
- So take a 18" x 8" rectangle from fabrics B and H and cut strips at a 45° making sure the width its 1½".




DIAGRAM 18

 Each of your strips now has their edges cut on bias which will work well for stitching them into a continuous strip.



 ${\rm DIAGRAM}~19$

- Place binding strips right sides together as shown on diagram 20, notice how there will be about ¼" fabric hanging over on each end, this will ensure your binding strips will form one straight continuous binding.
- Sew and trim excess fabric.






DIAGRAM 20

- Stitch strips of binding together until you have about 30" long binding.
- Fold binding in half lengthwise, wrong sides together. Press with hot iron.
- Take pot holder 1, fabric C facing up and two

 (2) of fabric K pocket pieces and place them
 on top of the unit making sure the rounded
 edges are lining up.
- Pin in place and take your binding fabric and re-pin the binding around the pot holder edge. Sew the binding, overlapping the ends to finish.



DIAGRAM 21

• Repeat the same for pot holder 2.



DIAGRAM 22

Napkins Construction

Take one (1) 15½" x 3½" rectangle from fabric
 J and place steam a seam to four (4) heart
 cutouts from fabric I.

- Distance each heart in an even distance and place them on top of fabric J and about ½" away from the edges.
- Once you are satisfied with the placement, apply hot iron pressing carefully.
- Edge stitch each piece with a blanket stitch or desired top stitch.




DIAGRAM 23

- Cut a 15" x 3" rectangle of steam-a-seam and place it on the wrong side of fabric J rectangle.
- Fold the top and bottom edge at a ¼" towards the wrong side of the fabric and iron it.
- Now place it on top of the 15½" rectangle from fabric F at a 2" distance from the bottom and edge stitch the top and bottom of fabric J piece.
- Iron the piece carefully so the steam-a-seam sticks to fabric **C**.





 Finish the hem of your napking by doing a baby hem all around fabric F.



DIAGRAM 25

• Repeat the same instructions in order to complete the second napkin. Enjoy!



Congratulations & enjoy



artgalleryfabrics.com

NOTE: While all possible care has been taken to ensure the accuracy of this pattern, We are not responsible for printing errors or the way in which individual work varies.

Please read instructions carefully before starting the construction of this quilt. If desired, wash and iron your fabrics before starting to cut.

© 2022 Courtesy of Art Gallery Quilts LLC. All Rights Reserved.

